

[Home](#) / [Xcyclopedia](#) / [Library](#) / **mode.com | DOS Device MODE Utility**

mode.com

- >> File Path: C:\Windows\system32\mode.com
- >> Description: DOS Device MODE Utility

Hashes

Type	Hash
MD5	59D1ED51ACB8C3D50F1306FD75F20E99
SHA1	AB7F4D369502697E54D6AB60F1B1711C114A0DDF
SHA256	D3E4FBE23E03704D6EE0A0C33A630E8A51E468383E6F72112A759EFD6795EBE1
SHA384	5135C98CB5E65E9AF2330BEDFE2992FFE6033AB42C986C0D89B4F688CFC177D8C33AE82E4B65BD6824FCA9E4189B1245
SHA512	DABBE2E81D7BEBBAF3ECB2BE704A1E71993807AE487DCEB8661DB88D0AA80DA2972C79F82D30418154CDE84D1F0FA43B244FC55BDEA05D696BFD9DA1FCD41DE4
SSDEEP	768:Q/MyUH4qPmdq4rQJNVytJtCosoxoaNlAyv1U:Q/1hcD8xtCLoxoajU
IMP	2F60C2ED7648C832822B0B1EE9787340
PESHA1	E2D18A9DCC3304038F0B402CDC95CA25525FFF3E
PE256	146CC98D5BADE9994D05A261C9C8082C80C20A3D7062C3D6C6463C1CA67A289E

Runtime Data

Usage (stdout):

```
Configures system devices.

Serial port:      MODE COMm[:] [BAUD=b] [PARITY=p] [DATA=d] [STOP=s]
                  [to=on|off] [xon=on|off] [odsr=on|off]
                  [octs=on|off] [dtr=on|off|hs]
                  [rts=on|off|hs|tg] [idsr=on|off]

Device Status:    MODE [device] [/STATUS]

Redirect printing: MODE LPTn[:]=COMm[:]

Select code page: MODE CON[:] CP SELECT=yyy

Code page status: MODE CON[:] CP [/STATUS]

Display mode:     MODE CON[:] [COLS=c] [LINES=n]

Typematic rate:   MODE CON[:] [RATE=r DELAY=d]
```

Loaded Modules:

Path
C:\Windows\System32\KERNEL32.DLL
C:\Windows\System32\KERNELBASE.dll
C:\Windows\system32\mode.com

C:\Windows\SYSTEM32\ntdll.dll

Signature

- >> Status: Signature verified.
- >> Serial: 3300000266BD1580EFA75CD6D3000000000266
- >> Thumbprint: A4341B9FD50FB9964283220A36A1EF6F6FAA7840
- >> Issuer: CN=Microsoft Windows Production PCA 2011, O=Microsoft Corporation, L=Redmond, S=Washington, C=US
- >> Subject: CN=Microsoft Windows, O=Microsoft Corporation, L=Redmond, S=Washington, C=US

File Metadata

- >> Original Filename: MODE.COM
- >> Product Name: Microsoft Windows Operating System
- >> Company Name: Microsoft Corporation
- >> File Version: 10.0.19041.1 (WinBuild.160101.0800)
- >> Product Version: 10.0.19041.1
- >> Language: English (United States)
- >> Legal Copyright: Microsoft Corporation. All rights reserved.
- >> Machine Type: 64-bit

File Scan

- >> VirusTotal Detections: 0/75
- >> VirusTotal Link:
https://www.virustotal.com/gui/file/d3e4fbe23e03704d6ee0a0c33a630e8a51e468383e6f72112a759efd6795ebe1/detection

Additional Info*

**The information below is copied from [MicrosoftDocs](#), which is maintained by [Microsoft](#). Available under [CC BY 4.0](#) license.*

mode

Displays system status, changes system settings, or reconfigures ports or devices. If used without parameters, **mode** displays all the controllable attributes of the console and the available COM devices.

Serial port

Configures a serial communications port and sets the output handshake.

Syntax

```
mode com<m>[:] [baud=<b>] [parity=<p>] [data=<d>] [stop=<s>] [to={on|off}] [xon={on|off}] [odsr={on|off}] [octs={on|off}] [dtr={on|off|hs}] [rts={on|off|hs}]
```

Parameters

Parameter	Description
com<m>[:]	Specifies the number of the async Prncnfg.vbshronous communications port.

<code>baud=</code>	Specifies the transmission rate in bits per second. The valid values include: 11 - 110 baud 15 - 150 baud 30 - 300 baud 60 - 600 baud 12 - 1200 baud 24 - 2400 baud 48 - 4800 baud 96 - 9600 baud 19 - 19,200 baud
<code>parity=<p></code>	Specifies how the system uses the parity bit to check for transmission errors. The valid values include: n - none e - even (default value) o - odd m - mark s - spaceNot all devices support using the m or s parameters.
<code>data=<d></code>	Specifies the number of data bits in a character. Valid values range from 5 through 8 . The default value is 7 . Not all devices support the values 5 and 6 .
<code>stop=<s></code>	Specifies the number of stop bits that define the end of a character: 1 , 1.5 , or 2 . If the baud rate is 110 , the default value is 2 . Otherwise, the default value is 1 . Not all devices support the value 1.5 .
<code>to={on off}</code>	Specifies whether the device uses infinite time out processing. The default value is off . Turning this option on means that the device will never stop waiting to receive a response from a host or client computer.
<code>xon={on off}</code>	Specifies whether the system allows the XON/XOFF protocol. This protocol provides flow control for serial communications, enhancing reliability, but reducing performance.
<code>odsr={on off}</code>	Specifies whether the system turns on the Data Set Ready (DSR) output handshake.
<code>octs={on off}</code>	Specifies whether the system turns on the Clear to Send (CTS) output handshake.
<code>dtr={on off hs}</code>	Specifies whether the system turns on the Data Terminal Ready (DTR) output handshake. Setting this value to on mode, provides a constant signal to show the terminal is ready to send data. Setting this value to hs mode provides a handshake signal between the two terminals.
<code>rts={on off hs tg}</code>	Specifies whether the system turns on the Request to Send (RTS) output handshake. Setting this value to on mode, provides a constant signal to show the terminal is ready to send data. Setting this value to hs mode provides a handshake signal between the two terminals. Setting this value to tg mode provides a way to toggle between ready and not ready states.
<code>idsr={on off}</code>	Specifies whether the system turns on the DSR sensitivity. You must turn this option on to use DSR handshaking.
<code>/?</code>	Displays help at the command prompt.

Device status

Displays the status of a specified device. If used without parameters, **mode** displays the status of all devices installed on your system.

Syntax

```
mode [<device>] [/status]
```

Parameters

Parameter	Description
<code><device></code>	Specifies the name of the device for which you want to display the status. Standard names include, LPT1: through LPT3:, COM1: through COM9:, and CON.
<code>/status</code>	Requests the status of any redirected parallel printers. You can also use /sta as an abbreviated version of this command.
<code>/?</code>	Displays help at the command prompt.

Redirect printing

Redirects printer output. You must be a member of the Administrators group to redirect printing.

[!NOTE] To set up your system so that it sends parallel printer output to a serial printer, you must use the **mode** command twice. The first time, you must use **mode** to configure the serial port. The second time, you must use **mode** to redirect parallel printer output to the serial port you specified in the first **mode** command.

Syntax

```
mode LPT<n>[:]=COM<m>[:]
```

Parameters

Parameter	Description
-----------	-------------

LPT <n> [:]	Specifies the number of the LPT to configure. Typically, this means providing a value from LTP1: through LTP3: , unless your system includes special parallel port support. This parameter is required.
COM <m> [:]	Specifies the COM port to configure. Typically, this means providing a value from COM1: through COM9: , unless your system has special hardware for additional COM ports. This parameter is required.
/?	Displays help at the command prompt.

Examples

To redirect a serial printer that operates at 4800 baud with even parity, and is connected to the COM1 port (the first serial connection on your computer), type:

```
mode com1 48,e,,b
mode lpt1=com1
```

To redirect parallel printer output from LPT1 to COM1, and then to print a file using LPT1, type the following command before you print the file:

```
mode lpt1
```

This command prevents the redirection the file from LPT1 to COM1.

Select code page

Configures or queries the code page info for a selected device.

Syntax

```
mode <device> codepage select=<yyy>
mode <device> codepage [/status]
```

Parameters

Parameter	Description
<device>	Specifies the device for which you want to select a code page. CON is the only valid name for a device. This parameter is required.
codepage	Specifies which code page to use with the specified device. You can also use cp as an abbreviated version of this command. This parameter is required.
select= <yyy>	Specifies the number of the code page to use with the device. The supported code pages, by country/region or language, include: 437: United States 850: Multilingual (Latin I) 852: Slavic (Latin II) 855: Cyrillic (Russian) 857: Turkish 860: Portuguese 861: Icelandic 863: Canadian-French 865: Nordic 866: Russian 869: Modern Greek This parameter is required.
/status	Displays the numbers of the current code pages selected for the specified device. You can also use /sta as an abbreviated version of this command. Regardless whether you specify /status , the mode codepage command will display the numbers of the code pages that are selected for the specified device.
/?	Displays help at the command prompt.

Display mode

Changes the size of the command prompt screen buffer

Syntax

```
mode con[:] [cols=<c>] [lines=<n>]
```

Parameters

Parameter	Description
con[:]	Indicates that the change applies to the Command Prompt window. This parameter is required.

cols= <code><c></code>	Specifies the number of columns in the command prompt screen buffer. The default setting is 80 columns, but you can set this to any value. If you don't use the default, typical values are 40 and 135 columns. Using non-standard values can result in the command prompt app problems.
lines= <code><n></code>	Specifies the number of lines in the command prompt screen buffer. The default value is 25, but you can set this to any value. If you don't use the default, the other typical value is 50 lines.
/?	Displays help at the command prompt.

Typematic rate

Sets the keyboard typematic rate. The typematic rate is the speed at which Windows can repeat a character when you press the key on a keyboard.

[!NOTE] Some keyboards don't recognize this command.

Syntax

```
mode con[:] [rate=<r> delay=<d>]
```

Parameters

Parameter	Description
con[:]	Specifies the keyboard. This parameter is required.
rate= <code><r></code>	Specifies the rate at which a character is repeated on the screen when you hold down a key. The default value is 20 characters per second for IBM AT-compatible keyboards, and 21 for IBM PS/2-compatible keyboards, but you can use any value from 1 through 32. If you set this parameter, you must also set the delay parameter.
delay= <code><d></code>	Specifies the amount of time that will elapse after you press and hold down a key before the character output repeats. The default value is 2 (.50 seconds), but you can also use 1 (.25 seconds), 3 (.75 seconds), or 4 (1 second). If you set this parameter, you must also set the rate parameter.
/?	Displays help at the command prompt.

Additional References

>> [Command-Line Syntax Key](#)

MIT License. Copyright (c) 2020-2021 Strontic.

FOLLOW:  STRONTIC.COM  TWITTER  GITHUB  INSTAGRAM  LINKEDIN  FACEBOOK  EMAIL  FEED

© 2022 STRONTIC. Theme: Jekyll & Minimal Mistakes.